
# **User Manual**

# CamView



# Seeing the video from anywhere

Version: 1.1

Date: Feb. 19 2008

For CamView v1.02.12

# **Table of Contents**

LIST OF FIGURES	4
CHAPTER 1 : INTRODUCTION	6
1.1. What is in this user manual?	6
CHAPTER 2 : INSTALL CAMVIEW PROGRAM	7
2.1. INSTALLATION STEPS	7
CHAPTER 3 : STARTUP AND THE LAYOUT OF CAMVIEW	.12
3.1. Startup CamView	.12
3.2. LAYOUT OF CAMVIEW	.12
3.3. VIDEO WINDOW LAYOUT	
CHAPTER 4 : CAMVIEW FUNCTIONS	.13
4.1. Auto Search	.13
4.2. IP CAM ONLINE STATUS INDICATOR	.15
4.3. Auto Reconnect	.16
4.4. Full Screen	.17
4.5. Full Window	.17
4.6. SNAPSHOT	.18
4.7. Recording	.18
4.7.1. Cyclic recording	19
4.7.2 Stop recording	19
4.8 SWAP FUNCTION	.19
4.9. Language	.20
CHAPTER 5 : MANAGE IP CAMS (CAM IDS)	.21
5.1. CAM LIST TAB	.21
5.2. Add an IP Cam (Cam ID) to CameraList folder	.21
5.3 Add a folder to CameraList folder	.22
5.4. PLAY AN IP CAM (ESTABLISH THE VIDEO SESSION)	.22
5.5. GET/SET THE SETTINGS OF THE IP CAM (CAM ID)	.23
5.6. CHANGE THE CAMERA NAME OR PASSWORD OR THE NAME OF A FOLDER	.24
5.7. DELETE AN IP CAM (CAM ID) OR A FOLDER	.25
5.8. PLAY A GROUP OF IP CAMS	.26
CHAPTER 6 : OPERATIONS FOR THE ACTIVE VIDEO SESSION	.28
6.1. PLAY THE VIDEO (ESTABLISH THE VIDEO SESSION)	.28

6.2. STOP THE VIDEO	
6.3. PAUSE AND RESUME THE VIDEO SESSION	
6.4. MUTE AND UN-MUTE THE AUDIO	
6.5. VIDEO INFORMATION BAR	
6.6. VIDEO SESSION PROPERTIES	
CHAPTER 7 : CAMPLAY	
7.1. STARTUP OF CAMPLAY	
7.2. LAYOUT OF CAMPLAY	
7.3. FILE TREE	
7.4. FILES INFORMATION	31
7.5. DIRECTORY SETTINGS	
7.6. PLAYBACK THE RECORDED FILE	
7.7. STOP PLAYING THE VIDEO	
7.8. PAUSE OR RESUME THE VIDEO PLAYBACK	
7.9. TAKE A SNAPSHOT	
7.10. Mute and un-mute	
7.11. FAST FORWARD AND SLOW FORWARD	
7.12. ZOOM IN AND ZOOM OUT	
7.13. OPEN SNAPSHOT FILE	
CHAPTER 8 : UNINSTALL CAMVIEW PROGRAM	
8.1. UNINSTALLATION STEPS	
CHAPTER 9 : UPGRADE CAMVIEW PROGRAM	
9.1. Upgrade CamView	
CHAPTER 10 : TROUBLESHOOTING	
10.1. COMMON ISSUES AND SOLUTIONS	
10.2. FREQUENTLY ASKED QUESTIONS	

# List of Figures

Figure 2-1 Install-welcome	7
Figure 2-2 Install-select package	8
Figure 2-3 Install-installation folder	8
Figure 2-4 Install-shortcut folder	9
Figure 2-5 Install-ready to install	9
Figure 2-6 Install-installing	10
Figure 2-7 Install-finished	10
Figure 2-8 no .NET framework	11
Figure 3-1 Layout of CamView	12
Figure 3-2 Video window layout	12
Figure 4-1 Auto search-1	13
Figure 4-2 Auto search-2	14
Figure 4-3 Web configure	14
Figure 4-4 IP address of CamID 001006123	15
Figure 4-5 IP Cam online status	16
Figure 4-6 Auto reconnect	16
Figure 4-7 Full screen and full window	17
Figure 4-8 Full window mode	17
Figure 4-9 Directory settings	18
Figure 4-10 Swap video window	20
Figure 4-11 Multi-Language	20
Figure 5-1 New camera	21
Figure 5-2 Add new camera	21
Figure 5-3 IP Cam account card	22
Figure 5-4 New folder	22
Figure 5-5 Name the folder	22
Figure 5-6 Play the video	23
Figure 5-7 Get video settings	24
Figure 5-8 Settings of the IP Cam	24
Figure 5-9 Authentication	24
Figure 5-10 ID/Password settings	25
Figure 5-11 Rename a folder	25
Figure 5-12 Delete an IP Cam	26
Figure 5-13 Delete a folder	26
Figure 7-1 Layout of CamPlay	30
Figure 7-2 File tree	31

Figure 7-3 File information	. 32
Figure 7-4 Directory settings	. 32
Figure 8-1 Uninstall CamView	.34
Figure 8-2 CameraList settings	.35
Figure 8-3 Recording and snapshot settings	.35
Figure 8-4 Removing CamView	.36
Figure 8-5 Uninstallation successful	.36
Figure 9-1 Microsoft .NET Framework detected	.37
Figure 10-1 Selected vs Non-selected video window	.40

# **Chapter 1 : Introduction**

CamView is a video management software which comes and works with the IC202(w) series IP Cameras. It is designed with the idea of truly user-friendly. With CamView, it is just a mouse-click away to see the video of your IP Camera and, surprisingly, neither technical knowledge nor complex settings is required. Each IC202(w) series IP Camera has a unique Camera ID (Cam ID, 9 digits long) and a password for login to see the video. Therefore, the only thing you need to remember for seeing the video is the Cam ID and the password. The following chapters will walk you through the process of installing and using CamVIew step by step.

1.1. What is in this user manual?

Chapter 1: Introduction

This chapter briefly describes what CamView is.

Chapter 2: Install CamView Program

This chapter guides you how to install CamView program step by step.

Chapter 3: Startup and the layout of CamView

This chapter shows you where to launch the CamView and the layout of it. <u>Chapter 4: CamView functions</u>

This chapter describes some functionalities of CamView.

Chapter 5: Manage IP Cams (Cam IDs)

This chapter teaches you how to manage your IP Cams.

Chapter 6: Operations for the active video session

This chapter explains the basic operations of CamView.

Chapter 7: CamPlay

This chapter guides you how to use CamPlay to playback the recorded files.

Chapter 8: Uninstall CamView Program

This chapter guides you how to uninstall CamView program step by step. Chapter 9: Update CamView Program

This chapter guides you how to update CamView program.

Chapter 10: Troubleshooting

This chapter describes some common issues and solutions, as well as frequently asked questions.

# Chapter 2 : Install CamView Program

# 2.1. Installation steps

To install CamView on the Microsoft Windows, follow the steps below. Step 1. Please close other windows applications to prevent the installation from any possible conflict.

Step 2. Insert the installation CD into your CD-ROM drive and find the CamViewInstaller-Vxxx.exe. Double click it to start the installation process and you will see the "Welcome" screen as shown in Figure 2-1.

Note: xxx of CamViewInstallerV-xxx.exe is the version number, for example, 1.02.12. Note: If you have installed CamView program in your computer earlier, then you have to uninstall it before installing a new one. The uninstaller will be invoked automatically. Please refer to <u>Chapter 8 - Uninstall CamView Program</u> and make sure you select "Yes. Keep it" to keep the settings of CameraList during the uninstallation.

1	CamView 1.02.12 Setup
,	Seeing the video from anywhere!!
	Welcome
	Welcome to the installer for CamView 1.02.12.
	It is strongly recommended that you exit all Windows programs before continuing with this installation.
	If you have any other programs running, please click Cancel, close the programs, and run this setup again.
	Otherwise, click Next to continue.
	Next > Cancel

#### Figure 2-1 Install-welcome

Step 3. Click Next and the "Select Package" screen will show up as shown in Figure 2-2. If you do not know whether Microsoft .Net Framework existed or not, just leave it as it is.

CamView 1.02.12 Setup	X
<b>Select Packages</b> Please select the program features that you wa	nt to install.
Program Features:	
.NET Framework 2.0	This is the main program of CamView. It has to be installed. ( 7.14 MB )
Total space required: 29.6 MB	
<u> &lt; B</u> ac	:k Next > Cancel

Figure 2-2 Install-select package

Note: If you are installing CamView on Microsoft Vista operating system, then you do not need to install the .NET Framework 2.0 because it is natively built-in within the Vista.

Step 4. Click Next and the "Installation Folder" screen will show up as shown in Figure 2-3.

🗟 CamView 1.02.12 Setup	×
Installation Folder Where would you like CamView to be installed?	
The software will be installed in the folder listed below. To select a dit location, either type in a new path, or click Change to browse for an ex Install CamView to:	i e i e i i i
C:\Program Files\CamView	C <u>h</u> ange
Space required: 29.6 MB Space available on selected drive: 14.54 GB	
< Back Next >	<u>C</u> ancel

Figure 2-3 Install-installation folder

Step 5. Click Next and the "Shortcut Folder" screen will show up as shown in Figure 2-4.

🗟 CamView 1.02.12 Setup	×
<b>Shortcut Folder</b> Where would you like the shortcuts to be installed?	
The shortcut icons will be created in the folder indicated below. If you don't want to use the default folder, you can either type a new name, or select an existing folder from the list.	
Shortcut Folder:	
CamView	~
Install shortcuts for current user only	
Make shortcuts available to all users	
< <u>Back</u> ancel	


Figure 2-4 Install-shortcut folder

Step 6. Click Next and a summary screen will show up as shown in Figure 2-5.

🔄 CamView 1.02.12 Setup		
<b>Ready to Install</b> You are now ready to install CamView 1.02.12		
The installer now has enough information to install CamView on your compute	er.	
The following settings will be used:		
Install folder: C:\Program Files\CamView		
Shortcut folder: CamView		
Please click Next to proceed with the installation.		
< Back Next > Cance	əl	

Figure 2-5 Install-ready to install

Step 7. Click Next and a progress screen will show up as Figure 2-6.



#### Figure 2-6 Install-installing

Step 8. If you checked Microsoft .Net Framework package earlier in "Select Package" screen and it is not installed yet, the installer of Microsoft .Net Framework will be executed and please press Next till the end of the installation of Microsoft .Net Framework (It will take you several minutes). Step 9. The installation successful screen will show up as shown in Figure 2-7.



#### Figure 2-7 Install-finished

Step 10. If you have not installed Microsoft .NET Framework 2.0 or later version before and did not select it to install, the last screen you see will be "No .NET Framework 2.0 or later version installed" instead of "Installation Successfully" as shown in Figure 2-8. In this situation, we recommend you to reinstall the CamView and do install the ".NET Framework 2.0" package.





Figure 2-8 no .NET framework

# Chapter 3 : Startup and the layout of CamView

# 3.1. Startup CamView

You can startup CamView from either Start  $\rightarrow$  Programs  $\rightarrow$  CamView or the shortcut of CamView on the windows desktop.

# Layout of CamView Figure 3-1 is the layout of CamView.



# 3.3. Video window layout

CamView supports 6 different video window layouts, see Figure 3-2. Click on the one you want to switch to.




Figure 3-2 Video window layout

# **Chapter 4 : CamView functions**

# 4.1. Auto Search

Auto search is a function that searches all the IC202(w) series IP Cameras on your LAN (Local Area Network). At the very beginning of CamView startups, CamView automatically does the auto search. To do auto search manually, you can either double click on the "Auto Search" folder or right click on the "Auto Search" folder and select "Auto search" as shown in Figure 4-1; besides, select it from menu bar Camera → Auto search, as shown in Figure 4-2, to have it search the IP Cameras. The results, Cam IDs, will be listed under "Auto Search" folder. With auto search, you can right click on the found Cam ID and select "Web configure", as shown in Figure 4-3, to access to its web page for further configuration. If you have the mouse cursor stop on a Cam ID in the Auto Search list, the IP address of that Cam ID will be shown up as shown in Figure 4-4.

Note1: The result of auto search is not saved to the computer. If you want to save it, please refer to <u>Chapter 5.2. - Add an IP Cam (Cam ID) to CameraList folder</u>.

Note2: The browser that CamView invokes while you click the "Web configure" is Microsoft Internet Explorer.

Note 3: If your computer is in the different LAN with the IP Cam, auto search will not be able to find that IP Cam.




Figure 4-1 Auto search-1






Figure 4-3 Web configure



# 4.2. IP Cam online status indicator

There is an IP Cam icon right in front of the Camera Name which indicates the online status of that IP Camera as shown in Figure 4-5. If the color of the IP Camera icon is red, it means that IP Camera somehow is offline and not responding. If the color is green, then the IP Cam is either in LAN or registered. If it is yellow, it denotes that the IP Cam is online but the connection between the IP Cam and CamView is not that good because one might be behind a router which has strict rules for the access.

Note: The IP Cam online status will be refreshed every 30 seconds automatically. Therefore, if you power off an IP Cam, the status might still be online within 30 seconds, either green or yellow. Please wait for 30 seconds to make sure if an IP Cam is online or not.



Note: The green icon indicates the IP Cam is online and responding, but not guarantees that the video session can be established one hundred percent.

# 4.3. Auto Reconnect

Auto Reconnect is a function that reconnects the video session automatically once the session is closed by the IP Camera, for example, the settings of the IP Cam has been changed or the Internet connection of the IP Cam has lost. To be noticed, if you stop playing proactively, the auto reconnect mechanism will not be activated. During reconnecting the video session, you can stop reconnecting it by right click on the display area and select "Stop". The default value of auto reconnect is enabled. You can disable it manually by right click on the display area and select "Auto Reconnect" to uncheck it as shown in Figure 4-6




Figure 4-6 Auto reconnect

# 4.4. Full Screen

To watch the video in full screen mode, simply double click on the display area as shown in Figure 4-7. In the full screen mode, you can double click on the screen to change back to the normal window mode.



Figure 4-7 Full screen and full window

# 4.5. Full Window

To watch the video in the full window mode, simply double click on the video information bar of that display area as shown in Figure 4-7. Similarly, double click on it again to change back to the normal window mode. Figure 4-8 is the example of full window mode.




Figure 4-8 Full window mode

# 4.6. Snapshot

To take a snapshot, simply click on the snapshot button  $\square$  on the video information bar. The directory to store the taken snapshot can be configured through menu bar Settings  $\rightarrow$  Directory as shown in Figure 4-9. Click the Browse button next to snapshot path to change the directory.

DirectorySettings			
Drive C: 14.52 GB left	Available disk space for recording.		
Recording : C:\Program Files\CamView\Recording <sup>L</sup>	Browse		
Recording Options			
If disk has : GB free space left	Select a different		
<ul> <li>Cyclic Recording</li> </ul>	folder for storing the		
<ul> <li>Stop Recording</li> </ul>	recorded files.		
Snapshot : C:\Program Files\CamView\Snapshot Browse			
OK Cancel	Select a different		
Figure 4-9 Directory settings	folder for storing the taken snapshots.		

# 4.7. Recording

To enable or start recording, simply click on the record button  $\checkmark$  on the video information bar. If the recording is enabled, the icon of the record button

will become this  $\checkmark$ . You can enable the recording function before playing the video or during the active video session. Similar to snapshot, the directory to store the recorded files can be changed through menu bar Settings  $\rightarrow$  Directory as shown in Figure 4-9. Click the Browse button next to recording path to change the directory. Moreover, you can choose to stop recording or do the cyclic recording when the available disk space reaches the settings you configured. The default reserved disk space is zero which means all the available disk space might be eaten up by the recording. Therefore, a change

is recommended. To playback the recorded files, refer to <u>Chapter 7 CamPlay</u>. *Note1: The recorded file will be split every 100 Megabytes.* 

Note2: It is highly recommended to change the directory to other drive instead of drive C because the drive C is the system drive mainly for the operating system.

#### 4.7.1. Cyclic recording

What cyclic recording does is removing the oldest recorded files, no matter what CamID it is, in the recording directory.

## 4.7.2 Stop recording

When available disk space reaches the setting you configured, it just stops recording but keeps playing the video. Whenever you want to stop recording during the active video session but still play the video, press the recording

button again – and the recording function will be turned off.

## 4.8 Swap function

Swap function is available for the layouts which have one video window bigger

than others, see Figure 4-10. Click the swap button  $\square$  to swap the current

video window with the biggest video window. The biggest video window of the layout is the one to be swapped out, so there is no swap button with it.

Note: The swap button will disappear when the sizes of all video windows of the layout are equal.



Figure 4-10 Swap video window

# 4.9. Language

CamView supports multi-language user interface. Currently English and traditional Chinese are supported. Please choose it from menu bar Language, see Figure 4-11.



Figure 4-11 Multi-Language

# Chapter 5 : Manage IP Cams (Cam IDs)

# 5.1. Cam list tab

CameraList is a list for storing individual Cam ID. Moreover, you can create folders to categorize the Cam IDs.

# 5.2. Add an IP Cam (Cam ID) to CameraList folder

There are two ways to add a Cam ID (IP Cam) to the CameraList. One is to right click on the CameraList folder, select "New camera" as shown in Figure 5-1, and fill in the camera name, Cam ID, and password to corresponding fields as shown in Figure 5-2.

🔁 CamView				
Camera View S	Settings	Language	Help	
Cam list				
₽-📴 CameraList				
📃 📕 CamID	)1	New Camera		
📃 📃 🧵 CamID	EcamID2 New Folder			
📃 🔚 🦉 CamID	)3	Rename		
📮 🔁 Test Fo	ole	Delete		

# Figure 5-1 New camera

Add New Camera		×	
Name : Cam ID :	New Camera		
Password :	•••••		
🗹 Save password			
Ad	dCancel	.::	

# Figure 5-2 Add new camera

Another way is to drag the Cam ID from the Auto Search list to CameraList folder directly and then right click on the Cam ID and select "ID / Password settings" to edit the camera name and the password information as shown in Figure 5-2.

Note: For default password (used for play video), please refer to the accompanied "ID /

Password Card" as shown in Figure 5-3.



Figure 5-3 IP Cam account card

5.3 Add a folder to CameraList folder

Adding a folder to CameraList folder is pretty simple, all you need to do is right click on the CameraList folder, select "New folder", and then fill in the folder name as shown in Figure 5-4 and Figure 5-5.

🔁 CamView	
<u> ⊂</u> amera <u>V</u> iew <u>H</u> elp	
Cam list Gro list	No Source
CameraList	New camera New folder Rename Delete
<u>Figure 5-</u>	4 New folder
Create New Folder	X
Folder New Fo	older
Ok	Cancel

Figure 5-5 Name the folder

Note: If you want to put Cam ID into the folder you created, just drag the Cam ID to that folder.

5.4. Play an IP Cam (establish the video session)

To play an IP Cam (Cam ID), you can do it by either double click on the Cam ID or right click on the Cam ID and select "Play on selected window" as shown in Figure 5-6.

🚳 CamView					
Camera V	ïew	Settings	Language	Help	
		E	Ē 🕢		No Source
Cam list					
📮 🞾 Can	neraL	.ist			
	CamI	D1			
	CamI	D2	Play on selec	ted window	/
	CamI	D3	ID / Passwor	d settings	
	Test		Video setting	s	
🛛 🖾 📁 Aut	io Sea	arc	Delete		
		_			

Figure 5-6 Play the video

5.5. Get/Set the settings of the IP Cam (Cam ID)

Right click on the Cam ID, select "Video settings", as shown in Figure 5-7, and the current settings of that IP Cam will be retrieved from the IP Cam and displayed as Figure 5-8. If you want to change the settings, choose new value for the item you want to change and press "Update" button. To change settings, the authentication, admin account and admin password, is required as shown in Figure 5-9. All the settings, of course, can be changed through the web page of the IP Cam. For the access to the web page, please refer to <u>Chapter 4.1</u> Auto Search – web configure.

Note1: Admin account and admin password are the same with the ones you used to login into the web page of the IP Cam. The default admin account is "admin" and the admin password is empty (no password). It is highly recommended to create the password right away. Note2: If you want to know more detail of the settings, please refer to the user manual of the IP Cam.

🛜 CamView				
Camera View S	Settings Language	e Help		
	III	No Sou	rce	
Cam list				
📮 🔁 CameraLi				
CamIC CamIC CamIC CamIC Test Auto Sea	)2 ID / Passv )3 Video set	elected window vord settings tings		
<u>Figu</u>	ıre 5-7 Get video	<u>settings</u>		
Settings - CamID1 / C	001001004	Camera n	ame / Cam ID	×
Resolution :	320x240	Place :	outdoor 🗸	J
Frame Rate :	15 👻	Light Freq. :	50 Hz 💉	
Bandwidth :	128 K 💌	Led Mode :	Normal	~
Microphone :	Disabled 💌	Brightness :	5	
Auto Select :	Enabled			
	Update	Cancel		

Figure 5-8 Settings of the IP Cam

Authentication	
Admin Account : Admin Password	[]
Ok	Cancel

Figure 5-9 Authentication

5.6. Change the Camera Name or password or the name of a folder

If you want to rename the camera name or change the password (for play video, not admin password) or rename a folder, right click on the Cam ID or the folder, select "ID / Password settings" for changing camera name or password, "Rename" for renaming the folder and change it as shown in Figure 5-10 and Figure 5-11.

🚭 CamView	
Camera View Sett	ings Language Help
	No Source
Cam list	
🗉 🕑 CameraList	
CamID1	
🛛 📕 CamID2	Play on selected window
📃 🔤 🖉 CamID3	ID / Password settings
📕 Test	Video settings
🛁 📁 Auto Search	Delete

Figure 5-10 ID/Password settings

🚾 CamVi	ew			
Camera	View	Settings	Language	Help
			ً ∢	
Cam lis	t			
	Cam Cam Cam	ID1 ID2 ID3 Foldor e	w Camera w Folder	
			elete	

Figure 5-11 Rename a folder

5.7. Delete an IP Cam (Cam ID) or a folder

Simply right click on the Cam ID or the folder you want to delete and select "Delete" to remove it as shown in Figure 5-12 and Figure 5-13.

🚳 CamVie	ew				
Camera	View	Settings	Language	Help	
			ā 📣 🛛		No Source
			, • J		
Cam list	:				
🕞 🧭 C	ameral	_ist			
	[ Cam]	ID1			
	[ Cam]	ID2			
	Cam]	ID3	Play on selec	ted window	v
<b>□</b> €	🕽 Test	Fol	ID / Passwor	d settings	
	— 🧵 Те	est 📃	Video settin <u>c</u>	8	
A 📬 🚽	uto Se	arcł	Delete		

Figure 5-12 Delete an IP Cam

🚭 CamView			
Camera View Sett	tings	Language	Help
		4	
Cam list			
CameraList			
ia - Dia Test Fol Intest Inte	۲ ۲	New Camera New Folder Rename Delete	

Figure 5-13 Delete a folder

# 5.8. Play a group of IP Cams

If you have setup a folder, say, Home, and there are 6 IP Cams in it. To play all the IP Cams in Home folder, simply double click on the Home folder. To be noticed, video window layout matters here. The maximum count of how many IP Cams in a folder could be played depends on how many video windows you have in current layout. For instance, if the current layout is 4-window, then only 4 IP Cams will be played which means the last 2 IP Cams will not be played. What if you want to play all 6 IP Cams in Home folder, simply change your video window layout to 6 or more!

# Chapter 6 : Operations for the active video session

There are some operations available to control the video session such as stop, pause, resume, mute, un-mute and so on. We will describe those operations in this chapter.

6.1. Play the video (establish the video session) Please refer to <u>Chapter 5.4.</u>

## 6.2. Stop the video

To stop a video session, right click on that display area, and select "Stop". If there are, for example, three video sessions and you want to stop all of them, either stop each of them one by one or select "Disconnect all" from menu bar, Camera  $\rightarrow$  Diconnect all, to disconnect all the active video sessions.

## 6.3. Pause and Resume the video session

To pause a video session, right click on that display area, and select "Pause". If you want to resume a paused video session, simply click "Pause" again to resume it. To pause all the active video sessions, select "Pause all" from menu bar, Camera  $\rightarrow$  Pause all. Likewise, click "Pause all" again to resume all the paused video sessions.

#### 6.4. Mute and Un-Mute the audio

Click on the speaker button  $\P$  to mute the audio. Click on button  $\P$  to

un-mute. This speaker controls all the audio come from each video session. If it is muted, you will not hear the audio from any active video session even the microphone of the IP Cam is enabled.

Note: Make sure you enable the "audio microphone" option in the settings of the IP Cam if you want to hear the voice.

# 6.5. Video information bar

There are some information displayed on the video information bar for each video session such as Camera Name, Frame rate, and the time of the IP Cam (remote time). If the video session is failed to establish, the failed reason will be displayed on the bar for user's diagnosis. We briefly explain the failed reasons below.

Unavailable: The IP Cam you are trying to connect is not registered to P2P

server or not responding.

Full user: The IP Cam you are trying to connect is full. The maximum users of an IP Cam can serve simultaneously are up to 20. However, it depends on the setting of video resolution of the IP Cam. Please refer to the user manual of the IP Cam for detailed information.

Password Error: It means the password for playing video you entered is incorrect.

Connecting: It means CamView is in the stage of connecting to the IP Cam. Reconnecting: It means CamView is in the stage of reconnecting to the IP Cam.

6.6. Video session properties


Currently, this shows almost the same information with the one on video information bar. The only difference in between is that video information bar shows failed reason if the video session is failed to be established.

# Chapter 7 : CamPlay

CamPlay is a management software for the recorded files and snapshots which were recorded or taken by the CamView earlier. You do not have to install it. It comes with the CamView. The main function of CamPlay is the playback function.

# 7.1. Startup of CamPlay

There are three ways to start CamPlay. First one is from the Start → Programs
→ CamView → CamPlay. Second one is from the menu bar of CamView View
→ CamPlay. Last one is from the shortcut of CamPlay on the windows desktop.



# 7.3. File tree

As you can from the Figure 7-1, the file tree has two lists. One is the Recorded

Files list which lists all the recorded files found in the directory of recording. Another one is the Snapshot Files list which lists all the snapshots found in the directory of snapshot. Both of recording files list and snapshot files list are 3-tier lists. The first tier is the CameraName-CamID, i.e. Home-001001001. The second tier is the date of the recording files or snapshots. The third tier is the file and it was named to the time of the video file been recorded or the snapshot been taken. See Figure 7-2 as the example. The file tree can be refreshed by either right click on the Record Files and click Refresh or from the menu bar CamPlay → Refresh file tree.




Figure 7-2 File tree

# 7.4. Files information

When you have your mouse cursor stop on the file, CamPlay shows the complete path of the file and the file size of it as shown in Figure 7-3.




Figure 7-3 File information

## 7.5. Directory settings

Similar to CamView, you can configure the directory from the menu bar  $\rightarrow$  Settings  $\rightarrow$  Directory as shown in Figure 7-4.

🕑 Directory settings	
Recorded files folder: C:\Program Files\CamView\Recording	Browse
Snapshot files folder: C:\Program Files\CamView\Snapshot	Browse
OK Cancel	

#### Figure 7-4 Directory settings

Note: To correctly find the video files and snapshots which were recorded and taken by CamView, we strongly suggest configuring the directories of the recorded files and snapshot files of CamPlay to what you have configured in CamView.

# 7.6. Playback the recorded file

To playback the recorded file, simply double click on the file and the recorded file will be played on the display area.

# 7.7. Stop playing the video

As you might know, just click on the stop button



7.8. Pause or resume the video playback

The pause button and resume button are the same one, . Click it to pause or resume the video playback.

# 7.9. Take a snapshot

To take a snapshot during the video playback, simply click the snapshot button

. The snapshots you taken within CamPlay are stored to snapshot\_directory\CamPlay\date\. Snapshot\_directory is the director you configured to store the snapshots.

7.10. Mute and un-mute

Mute button and un-mute button are the same one, \_\_\_\_\_. Click it to mute and un-mute.

#### 7.11. Fast forward and slow forward

There are two forward modes, fast forward and slow forward, supported by CamPlay. With fast forward, up to 8 times faster than the normal speed. With slow forward, up to 8 times slower than the normal speed. The button for fast

forward is and the button for slow forward is . Click play button

Þ

to change back to the normal speed.

# 7.12. Zoom in and zoom out

The maximum resolution you can zoom in to is 640x480 and the minimum resolution you can zoom out to is the original resolution of the video file. To

zoom in, click	Q. Click	e,	to zoom out and click	۹.	to change back
to the original r	esolution of	the	video file.		

# 7.13. Open snapshot file

Double click on the snapshot file and the default image viewer will be invoked automatically by the Microsoft Windows. Unlike playing the recorded file, the snapshot is not displayed in the display area. This gives you the ability to playback the recorded video file and view the snapshot at the same time.

# Chapter 8 : Uninstall CamView Program

8.1. Uninstallation steps


There are two ways to invoke the CamView uninstaller.

- 1. Uninstall from the start menu
  - .Start → CamView → Uninstall CamView
- 2. Uninstall from the control panel
  - .Start → Settings → Control Panel → Add or Remove Programs

.Select CamView program and click "Change/Remove".

.Follow uninstaller to remove the CamView.

Step 1: Once the CamView uninstaller has been invoked, the uninstall screen as shown in Figure 8-1 will show up. Press "Next" button to move on.





Step 2: Uninstaller asks you to choose whether to keep the current settings of CameraList or not as shown in Figure 8-2. Press "Next" to continue. Note: If you are updating CamView program, please select "Yes. Keep it". Otherwise, the settings will be cleaned up.



Figure 8-2 CameraList settings

Step 3: Uninstaller asks you if you want to remove the recorded files and snapshots or not as shown in Figure 8-3.

🗟 CamView Setup 🛛 🔀
Recording Folder and Snapshot Folder settings.
Do you want to remove the Recording folder and Snapshot folder , if any ? ○ Yes.I want to REMOVE it. ④ No.I do not want to remove it.Keep it.
< Back Next > Cancel

Figure 8-3 Recording and snapshot settings

Step 4: Figure 8-4 shows the progress of the uninstallation.




Figure 8-4 Removing CamView

Step 5: Once the CamView has been uninstalled successfully, the uninstallation finished screen as shown in Figure 8-5 will show up.




Figure 8-5 Uninstallation successful

# Chapter 9 : Upgrade CamView program

# 9.1. Upgrade CamView

Before upgrading newer CamView program, please remove previous version of CamView, if any. Get the new CamView program and refer to <u>Chapter 2 -</u> <u>Install CamView</u> for detail. Due to you have installed CamView before which also means you have installed Microsoft .NET framework as well. Therefore, please uncheck the ".NET Framework 2.0" while selecting packages during the installation. If you don't, installer will detect that you already have it installed. So no need to install it again! The message as shown in Figure 9-1 will show up to inform you that you are not going to install the .NET Framework again. Anyway, as long as the final screen of the installation you see is the "Installation successfully", CamView should work fine.

Microso	ft .NET Framework Detected 🛛 🔀
(į)	Microsoft .NET Framework 2.0 or later version is detected. Therefore, no need to install it again!
	ок

Figure 9-1 Microsoft .NET Framework detected

# **Chapter 10 : Troubleshooting**

This chapter consists of two parts, "Common Issues and Solutions" and "Frequently Asked Questions". If you come across any problem, please look it up to see if it answers your questions or dispels your doubts.

10.1. Common Issues and Solutions

Q: My computer is in the same LAN with the IP Cam, however, no IP Cam or Cam ID was found and listed in the auto search folder.

A: There are many possible causes for this problem as followings.

1. IP Cam problem

1.1. Make sure the IP Cam is alive by checking the power LED (red one). It should be on steadily.

1.2. Make sure the network connection of the IP Cam is configured correctly and workable.

2. CamView problem

2.1. If you start the CamView before your computer gets the IP address, then it will be unavailable. Please restart CamView after your network connection is available.

Q: I can not view the IP Cam's video. My computer is in different LAN with the IP Cam.

A: Normally, in the middle of the video information bar will display the brief reason for failing to play the video. Please refer to <u>Chapter 6.5. - Video</u> <u>information bar</u> for detail. In some special cases, if the firewall is on, the video stream might be blocked by the firewall.

Q: The IP Cam status indicator shows green icon, but I can not view the video or change the settings.

A: As mentioned in <u>Chapter 6.5. - Video information bar</u>, the green icon only denotes that the IP Cam is online and responding, not guarantees that the video session can be established one hundred percent. The reason is due to the firewall or the strict access rules of the router.

Q: The video quality is not that good when I view it remotely via the Internet.A: The video quality is greatly affected by your Internet connection speed.Therefore, we recommend you to change the bandwidth settings of the IP Cam to a value which is smaller than the one that your ISP provides you.

Q. The video quality is not good when the status indicator of the IP Cam shows yellow. Why is that?

A: If it is yellow, it means the connection between CamView and the IP Cam is not good. There might be a firewall in between or the routers that IP Cam or CamView are behind have strict rules for the access.

Q. The status indicator of the IP Cam shows green icon, however, I can not set the settings of the IP Cam.

A: The cause might be that the admin account and admin password you entered were incorrect. To be noticed, the admin password is not the same one with the password for playing video. The admin password is the same one with the one you used to login into the web page of the IP Cam. The default admin account is "admin" and default admin password is empty (no password).

10.2. Frequently Asked Questions

Q: Can the password for playing video be null?

A: No. For security issue, we do not allow users to make their passwords for playing video empty.

Q: Can I change the settings of the IP Cam through CamView? A: Yes, partially. You can change the resolution, frame rate, bandwidth, microphone, auto select, indoor/outdoor mode, light frequency, LED mode, and brightness settings of the IP Cam through CamView. The rest of the settings can only be configured via the web page of the IP Cam.

Q. Sometimes I failed to connect to the IP Cam (Cam ID) after changing the settings of the IP Cam.

A: IP Cam needs some time, around 5 seconds, to re-initialize the system. Therefore, please wait 5 seconds and try to connect it again for playing the video or getting the settings. If the auto reconnection is enabled, then CamView will connect it for you in 5 seconds.

Q. "Web configure" is available for the Cam ID under the Auto Search List. However, once I drag the Cam ID from Auto Search List to CameraList, the "Web configure" item is not available anymore. Why?

A: The IP Cams (Cam IDs) under the Auto Search List are located in the same Local Area Network with the CamView. Hence, the web page is accessible for sure. Regarding the Cam ID located in CameraList, there is no way to access to its web page if it is behind a router/NAT. Therefore, "Web configure" item will not be available for CameraList or GroupList.

Q: If there are 12 active video sessions, the audio I heard is from which video session?

A: The audio you heard is from the current selected window. See Figure 10-1.

